

MULTI-USER GUIDE ON CLIENT-SERVER SETUP

Kindly try any of the following methods listed below, to connect your Clients PC with Server PC.

METHOD 1: USING MOBILE HOTSPOT


1. Start the CBT Server on CBT Exam Software
2. Get a Mobile Phone or Tablet with Hotspot and SIM Card.
3. Switch on the Hotspot and Switch off Data.
4. Connect the Server PC and the Client PCs to same Mobile Hotspot.
5. Get the IP Address (i.e. IPv4 Address) of the Server PC.
6. [Click here to download IP Address Finder.](#)
7. Install it, then open it to get the IP Address of the Server PC instantly or use Command Prompt.
8. On the Client PCs, open any good internet browser (e.g. Google Chrome, Firefox, or Internet Explorer) and enter the Server IP Address gotten into the Address bar of your Clients browser.

METHOD 2: USING MIFI OR ROUTER

1. Start the CBT Server on CBT Exam Software
2. Get a Mifi or Router with a SIM Card.
3. Connect the Server PC and the Client PCs to same Mifi or Router Network.
4. Use Command Prompt to find IP Address on the server PC
5. To retrieve IP Address from your server PC, click on your Start Menu and type cmd in the search box and press enter. A black and white window will open where you will type ipconfig /all and press enter. There is a space between the command ipconfig and the switch of /all. Your IP address will be the IPv4 address.

```
IPv4 Address. . . . . : 192.168.43.38(Preferred)
```

6. On the Client PCs, open any good internet browser (e.g. Google Chrome, Firefox, or Internet Explorer) and enter the Server IP Address gotten into the address bar of your Clients browser.



NOTE:

- ❖ The methods above are for Mobile Hotspot and Wi-Fi Router connection setup, and does not require the use of internet data.
- ❖ When using Hotspot or Router, the Server PC and Client PCs must be connected to same Mobile Hotspot or Wi-Fi Router.
- ❖ If you are unable to successfully set-up the Client-Server WLAN Connection, Simply Disable your Antivirus and **Turn off Domain Network, Private and Public Network from Firewall & Network Protection** on the Server PC. Then launch the Software again from the Server PC.
- ❖ If you still have any challenge, feel free to contact our ICT Team on **+234-813-560-2553** or [click here](#) join our WhatsApp community for support.

For more information feel free to reach us via;

Call: +234-813-560-2553, +234-905-168-5732

WhatsApp: +234-813-560-2553, +234-907-036-5456

Email: enquiry@edusystems.com.ng

Website: www.edusystems.com.ng